

4.0 SP2 (4.0.2.0)  
May 2015  
702P03609



# Xerox® FreeFlow® Core Express

## Installation Guide



©2015 Xerox Corporation. All rights reserved. Xerox®, Xerox and Design®, and FreeFlow® are trademarks of Xerox Corporation in the United States and/or other countries.

Adobe and Adobe PDF are either registered trademarks or trademarks of Adobe Systems Incorporated in the United States and/or other countries.

Document version 1.2; May 2015

BR14621

# Table of Contents

- 1 Copyright.....ii
- 1 Prerequisites.....1-1
  - About This Guide.....1-1
  - Supported Operating Systems.....1-1
  - Supported Web Browsers.....1-2
- 2 Installing Xerox® FreeFlow® Core.....2-1
  - Xerox®FreeFlow® Core Licensing.....2-1
    - Trial License.....2-1
    - Production License.....2-1
  - Installing the Xerox® FreeFlow® Core Software.....2-2

## Table of Contents

# Prerequisites

## About This Guide

This guide provides simplified instructions for the most common Xerox® FreeFlow® Core installation. This guide covers:

- Use of the Xerox® FreeFlow® Core Preinstaller for:
  - SQL Server Express 2014 installation
  - System configuration
- Use of the Xerox® FreeFlow® Core installer
- Installing Easy Start workflows

### Note

Instructions for configuring Xerox® FreeFlow® Core to use Windows shared directories or to convert Microsoft Office documents are included in the comprehensive installation guides. The comprehensive installation guides may be obtained from the Drivers & Downloads section in the Xerox® FreeFlow® Core page: <http://xerox.com/automate>.

## Supported Operating Systems

- Windows Server 2012 R2 Update – Recommended for most production environments.
- Windows 8.1 Update (64-bit) – Recommended for production environments with light workloads.
- Windows Server 2008 R2 SP1

### Note

MSHotfix for Windows Server 2008 R2 SP1 required

## Prerequisites

<http://support.microsoft.com/default.aspx?scid=kb;en-US;2545227>

- Windows 7 SP1 (64-bit)

### Note

MSHotfix for Windows 7 SP1 required

<http://support.microsoft.com/default.aspx?scid=kb;en-US;2545227>

## Supported Web Browsers

- Internet Explorer 10 or higher via compatibility mode on Windows 7 (64-bit), Windows 8.1 Update (64-bit), Windows Server 2008 R2, Windows Server 2012, Windows Server 2012 R2 and Windows Server 2012 R2 Update
- Firefox 27 or higher on Windows 7 (64-bit), Windows 8.1 Update (64-bit), Windows Server 2008 R2, Windows Server 2012, Windows Server 2012 R2 and Windows Server 2012 R2 Update
- Firefox 27 or higher on Mac OS X 10.7 or later
- Safari 6.1.4 or higher on Mac OS X 10.7 or later

# 2

## Installing Xerox® FreeFlow® Core

This Xerox® FreeFlow® product is offered subject to your acceptance of the license agreement included with the software and is subject to limited warranty terms. See the Xerox® FreeFlow® Core Software License Agreement for details.

### Xerox® FreeFlow® Core Licensing

#### Trial License

Xerox® FreeFlow® Core may be installed in trial mode without a license. The trial version is fully functional for 45 days.

#### Production License

The Xerox® FreeFlow® Core Enablement Kit delivered with your order contains your Activation key(s) and Product Serial Number. Depending on your product configuration you will receive one or more Enablement kits with an Activation key for each module.

Xerox® FreeFlow® Core may be licensed during installation over the Internet. If the Xerox® FreeFlow® Core server does not have access to the Internet, you will need to obtain a license file using the Xerox Software Activation Portal:

1. Open the Software Activation Portal website:

<https://www.xeroxlicensing.xerox.com/activation/>

2. Enter your Activation Key. Click **Next**.
3. Enter all Xerox® FreeFlow® Core requested User Information. Click **Next**.
4. Review the license information.
  - Select **Back** to make changes.

- Select **Activate Another License** to redeem additional Activation Keys.
  - Once you have redeemed all Activation Keys, select **Save and Download License File** to save the file to the local system.
5. Close the web browser to exit the Software Activation Portal.

## Installing the Xerox® FreeFlow® Core Software

1. Install all Windows Updates.
2. Disable antivirus software during the installation process.
3. Ensure the Xerox® FreeFlow® Core system is configured with a static IP address.
4. If required, enable or download and install .Net Framework 3.5 SP1.
  - For Windows 7 or Windows Server 2008 R2:  
<http://windows.microsoft.com/en-us/windows/turn-windows-features-on-off#1TC=windows-7>
  - For Windows 8.1 Update:  
<http://technet.microsoft.com/en-us/library/dn482064.aspx>
  - For Windows Server 2012 (all releases):  
<http://technet.microsoft.com/en-us/library/dn482071.aspx>
5. Run the Xerox® FreeFlow® Core Preinstaller and follow the prompts to install SQL Server and perform system configuration. Use the default options, except for the following:
  - Check the box to use SQL Windows Authentication.
6. Reboot.
7. Run the Xerox® FreeFlow® Core Installer and follow the prompts to install Xerox® FreeFlow® Core.
8. When prompted for a license file, select **Add** or **Change license dat file** and select the license file using the open file dialog. Click **Next**.
9. Reboot.
10. Launch Xerox® FreeFlow® and create an Admin account when prompted.
11. Log out.
12. Unzip the Easy Starts and run the install.bat file to install the Easy Starts.





