

Kit Installation Instructions

Product(s):		Date:
	CX250_v1.1_SP2 for DocuColor 240/250	06/13/08
Title:		Page:
	Patch_Custom2Booklet	1 of 1
	Installation instructions	

Purpose

This software kit provides a CX250_v1.1_SP2 software update in response to a CX250 SPAR. Refer to the included customer letter for more information.

In the event of a CX250 system reinstall this software should be reapplied.

Kit Contents

Qty. Description	

- 1 Kit Installation Instructions
- 1 Customer Letter
- 1 Patch_Custom2Booklet.zip

Prerequisites

- Previous working knowledge with CX250_v1.1_SP2.
- The CX250 must be at version **1.1_SP2** prior to performing this install. This software is supplemental to the version **1.1_SP2** launch software.

Installation Instructions

NOTE: This software may be installed by the customer.

- ____1. Exit the Spire application.
- ____ 2. Extract Patch_Custom2Booklet.zip to the CX250 Windows desktop.
- ____ 3. Open the **Patch_Custom2Booklet** folder.
- ____4. Double-click on the **Install.exe** file. Follow the onscreen instructions. Click **Finish** to exit the installation wizard.
- ____ 5. Restart the system by clicking **Start > Shutdown > Restart**.
- ____ 6. After the system restarts, the Spire CX260 software will launch automatically.
- ____7. To verify that the patch was successfully installed, go to the **Help** menu, select **About**, and confirm that **Custom2Booklet** is listed next to **Updates**.

Uninstallation Instructions

- ___ 1. Exit the Spire application.
- ___ 2. Extract Patch_Custom2Booklet.zip to the CX250 Windows desktop.
- ____ 3. Open the Patch_Custom2Booklet folder.
- ____4. Double-click on the **Uninstall.exe** file. Follow the onscreen instructions.
- 5. Launch the Spire application and open Help > About to confirm that the patch was uninstalled successfully.

XOG SPAR Team